

# ZenBand

GUI guide for the only 2D PWEM solver you'll ever need!

# Contents


*Recommended by legends: Zyz*

- [Layout](#)
- [Panel 1 – PWEM parameters](#)
  - [Example – device parameters](#)
- [Panel 2: Tab1 – Band Diagram Calculations](#)
  - [Example – Calc Bands](#)
- [Panel 2: Tab2 – Omnidirectional Band Gap Calculations](#)
  - [Example – Calc OBG](#)
- [Panel 2: Tab3 – Field Calculations](#)
  - [Example – Calc Fields](#)
- [Panel 3 – Extra Parameters](#)
- [Importing data](#)
  - [Importing data: Python example](#)

ZenBand is the  
way to go, Brahs!



# Layout



The app is distinguished into three different panels:

Panel 1 – PWEM Parameters;

Panel 2 – houses functions for PWEM solver, separated into three tabs;

Panel 3 – Extra Parameters.

# Panel 1 – PWEM parameters

**PWEM parameters**

Lx	<input type="text" value="1"/>
Ly	<input type="text" value="1.0"/>
r	<input type="text" value="0.4"/>
r2	<input type="text" value="0.1"/>
Ellipse_length	<input type="text" value="1"/>
Ellipse_width	<input type="text" value="1.0"/>
eps1	<input type="text" value="1.0"/>
eps2	<input type="text" value="12.0"/>
P	<input type="text" value="11"/>
Q	<input type="text" value="11"/>
Nx	<input type="text" value="1024"/>
Ny	<input type="text" value="1024"/>
FontSize	<input type="text" value="16"/>
Device selection	<input type="text" value="Square"/> ▼
Select Mode	<input type="text" value="E"/> ▼

Here you can find general parameters that describe the device and computational performance.

Device's unit cell is described by these variables:

*Lx* and *Ly* – number of periods in the given direction;

*r* – size of the cylinder (normalized to lattice constant *a*);

*r2* – size of another cylinder (only works for the smaller *Ring* cylinder or second *Honeycomb* cylinder);

*Ellipse\_width/length* – controls the eccentricity of the cylinder;

*eps1* – dielectric permittivity of the cylinder;

*eps2* – dielectric permittivity of the slab;

*Device selection* – let's the user choose between *Square*, *Frame*, *Ring*, *Hex* and *Honeycomb* devices.

Computational performance can be adjusted with these parameters:

*P*, *Q* – number of spatial harmonics used for plane wave expansion. Run time increases exponentially. **The number must be odd!**


*Nx*, *Ny* – grid size for the unit cell.

*FontSize* – changes the fontsize of the matplotlib plots.


*Select mode* – selects the mode for iso-frequency contours and field distributions.

# Example – device parameters

Device selection: Square



Device selection: Honeycomb



# Panel 2: Tab1 – Band Diagram Calculations

Calc Bands Calc OBG Calc Fields

**Bands and iso-freq contours**

Enter N\_beta 50

Enter no. of bands 30

Lower omega limit 0.0

Upper omega limit 1.0

Plot Device

Calc Bands

**Parameters for iso-freq contours**

Bloch mode 2

No. of lines 10

Calc Iso-Freq Contours

Calc 3D Iso-Freq Contours

‘Bands and iso-freq contours’ parameters:

*Enter  $N_{\text{beta}}$*  – the number of beta vector points on the band diagrams and iso-frequency contours (for contours, it shows the number of lines and columns, e.g.  $50 \times 50 = 2500$ ).

*Enter no. of bands* – the number of photonic bands that are displayed on band diagram.

*Lower omega limit* – changes the lower limit of y axis in band diagrams.

*Upper omega limit* – changes the upper limit of y axis in band diagrams.


‘Parameters for iso-freq contours’ :

*Bloch mode* – selects which Bloch mode is displayed in iso-frequency contours.


*No. of lines* – selects the number of iso-frequency lines on the plot.



# Example – Calc Bands




The number of bands can not exceed  $P*Q$ !



‘Calc 3D Iso-Freq Contours’ button

Bloch mode → 2nd Bloch mode, *E mode*



# Panel 2: Tab2 – Omnidirectional Band Gap Calculations

Calc Bands Calc OBG Calc Fields

**Parameters for gaps and sweeps**  
no. of Bloch modes   
no. of bands   
Lower freq. limit   
Upper freq. limit   
Enter beta pt num   
Calc Gap

**Parameters for parameter sweep**  
min R   
max R   
min R2   
max R2   
No. of steps   
FPS val   
Param sweep for R  
Make gif

‘Parameters for gaps and sweeps’:

*no. of Bloch modes* – choose the highest order band gap to search for;

*no. of bands* – the number of photonic bands that are displayed on band diagram;

*Lower/Upper freq. limit* – changes the lower/upper limit of y axis in band diagrams;

*Enter beta pt num* - the number of beta vector points on the band diagrams .

‘Parameters for parameter sweep’:

*min R* – start value of cylinder radius;

*max R* – end value for cylinder radius;

*min/max R2* – start/end value for second cylinder radius (works for *Ring* and *Honeycomb* lattices);



*No. of steps* – select number of intermediate radius values;

*Fps val* – frames per second for .gif file.




# Example – Calc OBG

‘Calc Gap’ button





A top window is created that gives a detailed overview of the gaps.

‘Param sweep for R’ button



‘Make gif’ button



$\min R = 0.3$ ;  
 $\max R = 0.5$ ;  
 No. of steps = 40;  
 Fps = 10.

# Panel 2: Tab3 – Field Calculations

Calc Bands Calc OBG **Calc Fields**

**gif and field parameters**

Bloch mode no.

5

Frame Number

5

FPS value

16

Get field gif

**Field parameters**

beta\_x (\*pi/a)

1

beta\_y (\*pi/a)

1

Phase

0

Field type

Re(f)

Calc Fz

Calc Fx

Calc Fy

‘gif and field parameters’:

*Bloch mode no.* – choose the Bloch mode;

*Frame Number* – the number of frames for .gif file;

*FPS value* – frames per second of the .gif file.

‘Field parameters’:

*beta\_x(\*pi/a)* – point in the x direction in the reciprocal lattice of the field;

*beta\_y(\*pi/a)* – point in the y direction in the reciprocal lattice of the field;

Phase – shift the phase of the real field;

Field type – choose between real part of the field and intensity distributions for the graph.

*Recommended by legends: Snoop Dogg*




Fo sho, ZenBand  
is sticky icky icky!

# Example – Calc Fields


M point ( $\beta_x(*\pi/a) = 1, \beta_y(*\pi/a) = 1$ );  
 $Phase = 0$ ;  
 $Field\ type = Re(f)$ .

‘Get field gif’ button




*Frame number = 40;*  
*Fps value = 10;*  
*Mode = E.*


‘Calc Fz’ button



‘Calc Fx’ button



‘Calc Fy’ button



# Panel 3 – Extra Parameters

**EXTRA parameters**

Is material diagonally anisotropic?

Anisotropic parameters

eps1 =

eps2 =

Use imported data

Background

This panel is dedicated to extra, more advanced options that a user might want.


The first option is to define a diagonally anisotropic material. This is a separate option in order to save a fraction of computational time and for user convenience.

An option to import a custom device is also available. The program supports .mat and .npz files. More information on how to build custom structures will be presented later.


A user can choose between light and dark themes of the app to make the experience more pleasant in darker environments or to better match the figure color theme.

Since there are number of parameters to adjust, an option to save and load the parameters was added. Once every entry is filled, press the ‘Save parameters’ button. Whenever you want to go back to the parameters that were saved, press ‘Load parameters’ button. The feature also works after the app was closed.

Light mode



Dark mode



# Importing data

You can import data using .npy and .mat files. If band diagram or field distributions are wanted, it is very important that these parameters are defined:

Unit cell grid, direct lattice vectors, reciprocal lattice vectors, beta vector array, key points of symmetry, names of the key points of symmetry.

To calculate iso-frequency contour diagrams, key points of symmetry are not needed.

It is also important that the arrays are named correctly in such a manor (Python example):


```
data = {'er':ER, 'beta':beta, 't1':t1, 't2':t2, 'T1':T1, 'T2':T2, 'KP':KP, 'KT':KT} # for bands and fields;
```

```
data = {'er':ER, 'beta':beta, 't1':t1, 't2':t2, 'T1':T1, 'T2':T2} # for contours.
```


Make sure that primitive lattice vectors define the perimeter of the unit cell, because they are used for *plt.pcolor* plot coordinates!

**‘Parameter sweep for R’ and ‘Make gif’ buttons do not work when parameters are imported!**

Correct way to define vectors



Incorrect way



# Importing data: Python example

## Data for bands

```
1. import numpy as np
2. import matplotlib.pyplot as plt

3. #####
4. # initialize parameters
5. er1 = 1
6. er2 = 12
7. r = 0.45
8. N_Points = 100

9. x = np.linspace(-0.5, 0.5, 1024)
10. y = np.linspace(-0.5, 0.5, 1024)
11. X,Y = np.meshgrid(x, y)
12. #####

13. ER = np.zeros((len(x), len(y)))

14. # define the shape
15. ER = ER + (X**2 + Y**2 > r**2)
16. ER = er1 + (er2 - er1) * ER
17. # plt.pcolor(ER)
18. ##### Bands #####

19. # define beta vectors
20. beta = np.zeros((2, N_Points))
21. beta[0, 0:29] = np.linspace(0, np.pi, 29); beta[0, 29:59] = np.pi;      beta[0,
59:100] = np.linspace(np.pi, 0, 41)
22. beta[1, 0:29] = 0;      beta[1, 29:59] = np.linspace(0, np.pi, 30); beta[1,
59:100] = np.linspace(np.pi, 0, 41)

23. # define names of key points of symmetry
24. KP = ['$\Gamma$', '$X$', '$M$', '$K$']

25. # define key points of symmetry
26. KT = [0, 29, 58, 99]

27. # define direct lattice vectors
28. t1 = np.array([[1],[0]])
29. t2 = np.array([[0],[1]])

30. # define reciprocal lattice vectors
31. T1 = 2*np.pi * np.array([[1],[0]])
32. T2 = 2*np.pi * np.array([[0],[1]])

33. data = {'er':ER, 'beta':beta, 't1':t1, 't2':t2, 'T1':T1, 'T2':T2, 'KP':KP, 'KT':KT}
34. np.save('import_sample.npy', data)
```

## Data for contours

```
1. import numpy as np
2. import matplotlib.pyplot as plt

3. #####
4. # initialize parameters
5. er1 = 1
6. er2 = 12
7. r = 0.45
8. N_Points = 100

9. #####

10. ER = np.zeros((len(x), len(y)))

11. # define the shape
12. ER = ER + (X**2 + Y**2 > r**2)
13. ER = er1 + (er2 - er1) * ER
14. # plt.pcolor(ER)
15. ##### Contours #####

16. # define beta vectors
17. bx = np.linspace(-np.pi, np.pi, N_Points)
18. by = np.linspace(-np.pi, np.pi, N_Points)
19. beta = np.zeros((2, N_Points*2))

20. idx = 0

21. for nx in range(0, N_Points):
22.     for ny in range(0, N_Points):
23.         beta[:,idx] = np.array([[bx[nx], by[ny]]])
24.         idx = idx + 1


25. # define direct lattice vectors
26. t1 = np.array([[1],[0]])
27. t2 = np.array([[0],[1]])

28. # define reciprocal lattice vectors
29. T1 = 2*np.pi * np.array([[1],[0]])
30. T2 = 2*np.pi * np.array([[0],[1]])

31.

32. data = {'er':ER, 'beta':beta, 't1':t1, 't2':t2, 'T1':T1,
'T2':T2}
33. np.save('import_sample.npy', data)
```

*Recommended by legends: Big Chungus*



I'm telling ya Doc,  
use ZenBand!